Job Logs Job Logs

Job Logs

This subsection covers the following topics:

- Job Logs
- Displaying the Log Terminated Jobs
- Column Headings: Log Report

Job Logs

The following options on the Reporting Menu offer information on jobs, which is extracted from the Entire Operations Log:

• Log - Terminated Jobs

Displays a log of all jobs that terminated OK.

• Log - Abended Jobs

Displays a log of all jobs that ended abnormally.

• Log - Jobs not started

Displays a log of all jobs that were not started, jobs whose latest start time was exceeded, jobs waiting for input conditions or jobs for which a permanent error has occurred during activation or start.


The following applies to all job logs:

Only those networks are displayed for which the user has read access.

The user has read access, if:

- 1. the user has profile type **A** (Administrator);
- 2. the owner SYSDBA is currently assigned to the user;
- 3. the network owner can be found on the user's owner list;
- 4. access to the network has been explicitly granted to the user (see the subsection Authorizing Other Users to Access a Network in the section Network Maintenance).

Displaying the Log - Terminated Jobs



1. Type its option number in the Option field on the Reporting Menu. Press Enter.

The following window opens in which you can enter a date range for which to display the information (default is current date):

Copyright Software AG 2001

```
02.11.01 *** Entire Operations 4.1.1 *** 14:33:31
Owner EXAMPLE Reporting Menu User ID GHH
    Reporting Menu
  1 Log - Terminated Jobs
  2 Log - Abended Jobs
  3 Log - Jobs not started
  4 Accounting Data
  5 Network Description (shor +-----+
  6 Network Description (deta!
    Network Job Flow Display ! Log - Terminated Jobs
  8 Schedule of Jobs
 9 Network Activation Summar! Start Date ===> 02.11.01
10 Network Schedule Overview! Time ===> 00:00:00
                                 Time ===> 00:00:00
                           !
                           ! End Date ===> 02.11.01
                                  Time ===> 23:59:59
Command => 1____
                          _ ! Enter
                                                   PF3 End
Enter-PF1---PF2---PF3---PF4---P +-----+ 12---
     Help End
                                                              Menu
```

2. Enter the required date range. Press Enter.

The following window opens:

```
*** Entire Operations 4.1.1 *** 14:33:31
PLE Reporting Menu User ID GHH
20.11.01
Owner EXAMPLE
    Reporting Menu
                      +----+
  1 Log - Terminated J !
                           Log - Terminated Jobs
  2 Log - Abended Jobs!
  3 Log - Jobs not sta!
  4 Accounting Data ! Owner ==> _____ * Select Blank All ! 5 Network Descriptio ! Network ==> ____ * Select Blank All !
  6 Network Descriptio!
  7 Network Job Flow D ! PF3 End
  8 Schedule of Jobs +-----
 9 Network Activation Summar ! Start Date ===> 20.11.01 !
10 Network Schedule Overview ! Time ===> 00:00:00 !
                                 Time ===> 00:00:00
                           !
! End Date ===> 20.11.01
! Time ===> 23:59:59
                                 Time ===> 23:59:59
                                                               !
Command => 1__
                                                    PF3 End
                           _! Enter
Enter-PF1---PF2---PF3---PF4---P +------+ 12---
     Help End
```

3. Enter owner and network for which to display information. You can enter selection criteria with an asterisk *. Press Enter.

The following screen appears:

Owner	Network	Job	Run	Date	Time	Message
SN	BS2-EX-2	SYM-1	109	10.11.01	00:01	Ended ok
EXAMPLE	E60-FLOW	JOB-01	997	10.11.01	13:15	Ended ok
EXAMPLE	E60-FLOW	JOB-012	997	10.11.01	13:28	Ended ok
EXAMPLE	E60-FLOW	JOB-013	997	10.11.01	13:31	Ended ok
EXAMPLE	E60-FLOW	JOB-014	997	10.11.01	13:44	Ended ok
EXAMPLE	E60-FLOW	JOB-019	997	10.11.01	14:25	Ended ok
EXAMPLE	E60-FLOW	JOB-02	997	10.11.01	14:27	Ended ok
EXAMPLE	E60-FLOW	JOB-04	997	10.11.01	14:39	Ended ok
EXAMPLE	E60-FLOW	JOB-06	997	10.11.01	14:41	Ended ok

The display of Log - Abended Jobs and of Log - Jobs not started also has the same format.

Column Headings: Log Report

Meaning of column headings:

Column	Description	
Owner	Owner to whom the network belongs.	
Network	Network to which the job belongs.	
Job	Job name as defined to Entire Operations.	
Date	Date of this event.	
Time	Time of event.	
Message	Message text.	

4. Press PF11 (Right) to scroll right and display the full message text. Press PF10 (Left) to scroll back to the left.

Press Enter to scroll down and display more log entries, if there are any.

5. Press PF3 (End) to return to the Reporting Menu.

Copyright Software AG 2001 3